

## LTTng-tools - Bug #1059

### The save and load commands do not use the same default home directory

08/25/2016 09:28 AM - Philippe Proulx

<b>Status:</b>	Confirmed	<b>Start date:</b>	08/25/2016
<b>Priority:</b>	Normal	<b>Due date:</b>	
<b>Assignee:</b>		<b>% Done:</b>	0%
<b>Category:</b>		<b>Estimated time:</b>	0.00 hour
<b>Target version:</b>			

#### Description

The save command does not consider the LTTNG\_HOME environment variable (nor HOME) because it uses `utils_get_user_home_dir()`, whereas the load command uses `utils_get_home_dir()`.

Therefore if LTTNG\_HOME is set (or if \$HOME has a different value than the entry in `/etc/passwd`), a save and load sequence does not find the session configuration file.

To remain consistent, I think the value of `utils_get_home_dir()` should be sent from the client to the session daemon at save time, so that, from the user's perspective, both commands are synchronized on the same environment variables.

Use case: this bug makes the save/load operations impossible to do in a virtual environment.

#### History

#1 - 08/25/2016 04:07 PM - Jérémie Galarneau

- Status changed from New to Confirmed